

Â

TELNET (TELEtype NETwork) is a network protocol used on the Internet or local area network LAN connections.

Â

The telnetd program (telnet server) is a server which supports the DARPA telnet interactive communication protocol. Telnetd is normally invoked by the internet server inetd or xinetd for requests to connect to the telnet port as indicated by the /etc/services file. Usually telnet listen on port TCP port 23.

Telnet is an insecure protocol and it is recommended that you use ssh server. But some time you really need telnet then first install telnet server as according to version of Linux distribution.

Telnet server installation

WARNING! Installing telnet open your computer to unencrypted network communication, which is a bad idea. If possible avoid telnet; and use secure shell called ssh.

Debian/Ubuntu Linux user type the following command:

```
# apt-get install telnetd
```

OR

How to install & turn on telnet service on RHEL, Fedora, CentOS, Ubuntu, FreeBSD, Debian

Written by Rudy

Saturday, 01 September 2012 10:04 - Last Updated Sunday, 02 September 2012 07:35

```
$ sudo apt-get install telnetd
```

Fedora Linux user the following command:

```
# yum install telnet-server telnet
```

Red Hat enterprise Linux user type the following command:

```
up2date telnet-server telnet
```

FreeBSD user type the following command:

No need to install new (telnet server) package, it is installed by default (/usr/libexec/telnetd)

Configure telnet server (turn on telnet server)

Again each distribution has its own method to turn on or off telnet service; same applies to telnet UNIX/Linux server.

If you are using **Red Hat / Fedora Linux**

The configuration file for telnet is /etc/xinetd.d/telnet. To enable telnet server you need to open this file and make sure disable = no read as disable = yes.

Alternately,

```
# chkconfig telnet on
```

How to install & turn on telnet service on RHEL, Fedora, CentOS, Ubuntu, FreeBSD, Debian

Written by Rudy

Saturday, 01 September 2012 10:04 - Last Updated Sunday, 02 September 2012 07:35

To start telnet server type command:

```
# /etc/init.d/xinetd restart
```

If you are using **Debian Linux**

The configuration file for telnet is /etc/inetd.conf. By default it is enabled when you install telnet server. To start telnet server type command:

```
# /etc/init.d/inetd restart
```

If you are using **FreeBSD**

The configuration file for telnet is /etc/inetd.conf. Open file using vi text editor and uncomment line:

```
# vi /etc/inetd.conf
```

Make sure commented line:

```
#telnet stream tcp nowait root /usr/libexec/telnetd telnetd
```

Read as follows:

```
telnet stream tcp nowait root /usr/libexec/telnetd telnetd
```

How to install & turn on telnet service on RHEL, Fedora, CentOS, Ubuntu, FreeBSD, Debian

Written by Rudy

Saturday, 01 September 2012 10:04 - Last Updated Sunday, 02 September 2012 07:35

Save and close the file. Start telnet service:

Enable inetd service so that telnet get loaded:

```
# vi /etc/rc.conf
```

Append/add following line to configuration file:

```
inetd_enable="YES"
```

Save and close the file, Restart telnet via inetd service:

```
# /etc/rc.d/inetd restart
```

Telnet to server (How do I use telnet client?)

You should now be able to telnet to the server from Windows or Linux desktop system. Type the following command to connect to Telnet server:

```
telnet server-ip-address  
telnet 192.168.1.5
```

How to install & turn on telnet service on RHEL, Fedora, CentOS, Ubuntu, FreeBSD, Debian

Written by Rudy

Saturday, 01 September 2012 10:04 - Last Updated Sunday, 02 September 2012 07:35

The configuration file for telnet is /etc/inetd.conf. By default it is enabled when you install telnet server. To start telnet server type command: You should now be able to telnet to the server from Windows or Linux desktop system. Type the following command to connect to Telnet server