Adding multiple ip ranges in Linux

Written by Friends Sunday, 02 March 2014 22:43 -

Say for example if you want to add the following different ip ranges in your server on the **Ethern** et port eth0

. Here are few simple steps to add the ip ranges in few minutes.

IP Block: 204.45.89.130-134 IP Block: 204.45.90.2-6 IP Block: 204.45.90.10-14 IP Block: 204.45.90.18-22 IP Block: 204.45.90.26-30

The above example has around 6 ranges with different ip sets. You can make use of the 'ifcfg-eth0-rangeX'

' feature to get this done simply. Ssh your server as root.

- # cd /etc/sysconfig/network-scripts

Create a file named ifcfg-eth0-range0

- # vi ifcfg-eth0-range0

Adding multiple ip ranges in Linux

Written by Friends Sunday, 02 March 2014 22:43 -

Add the following lines as below to add the first set of range (iee.. 204.45.89.130-134)

ONBOOT=yes
IPADDR_START=204.45.89.130
IPADDR_END=204.45.89.134
NETMASK=255.255.255.248
CLONENUM_START=1

Save your works and exit. Restart the network service using 'service network restart'. To add the second range you need to create another file called'

ifcfg-eth0-range1

' with the

CLONENUM START

start with

5

(setting up the number in

CLONENUM START

is very important here to avoid the ip overwritten, as the first range will use up to the eth0:4

the second range should start with

eth0:5

to work properly).

ONBOOT=yes
IPADDR_START=204.45.90.2
IPADDR_END=204.45.90.6
NETMASK=255.255.255.248
CLONENUM_START=5

Adding multiple ip ranges in Linux

Written by Friends Sunday, 02 March 2014 22:43 -

Save your works and restart the network service. You can do the same for the other ip ranges left with carefully numbering the **CLONENUM_START**. Use the **ifconfig** command to check the **eth0:X** number

everytime you restarts. After adding all the ranges, use ping to check the ips to make sure they are added properly.