

How to Clone a CentOS Server with Rsync

Written by BiRU

Monday, 02 September 2024 10:15 -

Cloning is the practice of cloning an exact copy of an existing Live Linux server using the [rsync command-line tool](#)

. Cloning requires 2 instances of servers – the server to be cloned and the destination server where the cloning process will occur. The rsync command-line tool [synchronizes all the files and directories](#) from the server being cloned to the destination server.

In this guide, you will learn how to hot clone a CentOS server with Rsync file synchronization tool.

Lab Setup

Here's the lab setup that we are using for this guide.

- Source Server – CentOS 7 – 192.168.2.103
- Destination Server – CentOS 7 – 192.168.2.110

The source server is the one we are going to clone onto the destination server.

Setup and Requirements

Before proceeding, ensure that you have met the prerequisites below:

- Both servers need to be running the same release of the operating system i.e CentOS 7.x, CentOS 8.x, etc.

- Additionally, the servers should have identical file systems and the same hard disk configuration i.e whether single-disks or in RAID configuration.

NOTE: Before hot cloning, ensure you disable all the services that involve shipping or writing

How to Clone a CentOS Server with Rsync

Written by BiRU

Monday, 02 September 2024 10:15 -

data e.g databases, mail service, etc.

CentOS

Step 1: Installing the Rsync Tool in

For cloning to be successful the rsync command-line tool needs to be present on both servers. This will be used for mirroring the source server to the destination server and syncing all the differences between the two systems. Thankfully, modern systems come with rsync already pre-installed.

To check the version of rsync installed run:

```
$ rsync --version
```

If you want to view additional information about rsync, execute the following [rpm command](#) :

```
$ rpm -qi rsync
```

How to Clone a CentOS Server with Rsync

Written by BiRU

Monday, 02 September 2024 10:15 -

tecmint@centos7:~

File Edit View Search Terminal Help

```
[tecmint@centos7 ~]$ rpm -qi rsync
Name           : rsync
Version        : 3.1.2
Release        : 10.el7
Architecture   : x86_64
Install Date   : Sun 19 Jul 2020 07:44:31 AM EDT
Group          : Applications/Internet
Size           : 834602
License        : GPLv3+
Signature      : RSA/SHA256, Fri 03 Apr 2020 05:07:22 PM EDT, Ke
Source RPM     : rsync-3.1.2-10.el7.src.rpm
Build Date     : Wed 01 Apr 2020 12:23:51 AM EDT
Build Host     : x86-02.bsys.centos.org
Relocations    : (not relocatable)
Packager       : CentOS BuildSystem <http://bugs.centos.org>
Vendor         : CentOS
URL            : http://rsync.samba.org/
Summary       : A program for synchronizing files over a network
Description    :
Rsync uses a reliable algorithm to bring remote and host file
systems into sync.

$ sudo yum install rsync
```

Step 2: Configure the Source Server

There are directories and files that you may want to exclude from cloning because they are either already available in the destination server or are autogenerated. These include the /boot, /tmp and /dev directories.

Therefore, create an exclusion file /root/exclude-files.txt and add the following entries:

```
/boot /dev /tmp /sys /proc /backup /etc/fstab /etc/mstab /etc/mdadm.conf
/etc/sysconfig/network*
```

Save and exit the configuration file.

How to Clone a CentOS Server with Rsync


Written by BiRU

Monday, 02 September 2024 10:15 -

Step 3: Clone the CentOS Server

With everything set, proceed and rsync your server to the remote or destination server using the command:

```
$ sudo rsync -vPa -e 'ssh -o StrictHostKeyChecking=no' --exclude-from=/root/exclude-files.txt /  
REMOTE-IP:/
```



```
tecmint@centos7:~  
File Edit View Search Terminal Help  
[tecmint@centos7 ~]$ sudo rsync -vPa -e 'ssh -o Str  
m=/root/exclude-files.txt / 192.168.2.110:/  
[sudo] password for tecmint:  
Warning: Permanently added '192.168.2.110' (ECDSA)  
root@192.168.2.110's password:  
sending incremental file list  
etc/  
etc/resolv.conf  
          78 100%    0.00kB/s    0:00:00 (xfr#1,  
etc/cups/  
etc/cups/subscriptions.conf  
          411 100%    0.40kB/s    0:00:01 (xfr#2,  
etc/cups/subscriptions.conf.0  
          111 100%    0.11kB/s    0:00:01 (xfr#3,  
etc/tuned/active_profile  
          14 100%    0.00kB/s    0:00:00 (xfr#4,  
etc/tuned/profile_mode  
           5 100%    0.03kB/s    0:00:00 (xfr#5,  
home/james/  
home/james/.ICEauthority
```

Clone CentOS Server

The command will rsync everything from the source server to the destination server while excluding the files and directories you defined earlier on. Be sure to replace the REMOTE-IP: option with your destination server's IP address.

After the syncing is done, reboot the destination system to reload the changes and thereafter,

How to Clone a CentOS Server with Rsync

Written by BiRU

Monday, 02 September 2024 10:15 -

boot into the server using the source server's credentials. Feel free to decommission the old server since you now have a mirror copy of it.